

those for other metals on the basis of strain rather than pressure change we have set $dP = -B_T d \ln V = -3B_T d \ln r$, thus defining $d \ln r$. The quantities $-d \ln C / d \ln r$ in Table 2 then measure the fractional change in stiffness divided by an average linear strain. For all constants this quantity is large in cadmium.