

Fig. 2. In K vs. In P-Ferric halides

Fig. 3. In K vs. In P-Acetylacetonate and basic acetate.

much over 90% are difficult to establish accurately, so one cannot say whether this description is applicable at very high dilution. For the halides, as well as for several other compounds which can be classified as relatively ionic,  $B \simeq 0.5$  with little temperature dependence. This corresponds to values of  $\Delta \vec{V}$  which range from about 1.2 cc at 10 kilobars to about 0.06 cc at 200

Table	1.	Constants	A	and	B	for	the	relationship
K =	AF	DB.						

Material	Temper- ature (°K)	A	В	
FeCla	295	0.265	0.564	
FeBr3	295	0.076	0.426	
KFeC14	295	0.091	0.497	
FePO <sub>4</sub>	295	0.079	0.457	
Fe Citrate	295	0.112	0.350	
K <sub>3</sub> Fe(CN) <sub>6</sub>	295	0.109	2.06	
Fe acetylacetonate	295	$1.2 \times 10^{-5}$	2.23	
Fe acetylacetonate	375	$0.96 \times 10^{-2}$	1.01	
Fe basic acetate	378	$0.22 \times 10^{-6}$	3.05	
Fe basic acetate	418	$2.21 \times 10^{-2}$	0.98	
Fe oxalate	295	0.041	0.51	
Fe oxalate	335	0.029	0.83	
Fe oxalate	383	0.043	1.146	
Strontium Fe				
oxalate	295	0.115	0.301	
Strontium Fe				
oxalate	383	0.058	0.844	
FeCla · 6H2O	294	0.063	0.95	
FeFa . 3H2O	294	0.027	0.95	
FeFa . 3H2O plus				
excess H <sub>2</sub> O	294	0.072	0.95	
FeCl <sub>2</sub> • 6NH <sub>3</sub>				
< 25 kbar	294	$2.4 \times 10^{-6}$	4.06	
FeCla . 6NH3				
> 25 kbar	294	0.46	0.27	
Fe(NCS)3 . 6H2O	295	0.136	0.528	
K <sub>3</sub> Fe(NCS) <sub>6</sub>	295	0.024	0.692	
Hemin	294	$5.5 \times 10^{-3}$	1.53	
Hemin	335	$4.2 \times 10^{-4}$	2.04	
Hemin	367	$3.5 \times 10^{-5}$	2.57	
Hematin	294	$2.7 \times 10^{-5}$	2.67	
Hematin	343	$1.4 \times 10^{-7}$	3.77	
nomatin	543	1.4 V 10 .	5.11	

28 FEBRUARY 1969

kilobars. As discussed later, the conversion introduces stresses in the neighborhood of the reduced site. One can insert a term of the form

## $-\Sigma \varepsilon_i d\sigma_i$

in the free energy, where  $\varepsilon$  and  $\sigma$  refer to strains and stresses introduced by the reduction. Then the  $\Delta V$  of Eq. 2 can be written:

$$\Delta \overline{V} = \Delta V' - \sum_{i} e_{i} \frac{\partial \sigma_{i}}{\partial p} \qquad (4a)$$

or, in the language of solution theory:

$$\Delta \overline{\mathcal{V}} = \Delta \mathcal{V}' - \frac{\partial \mathcal{V}_e}{\partial \mathcal{C}_{II}}$$
(4b)

where  $\Delta V'$  is the difference in unstrained volumes of the ferric and the ferrous site, and  $V_e$  is the excess volume of mixing. Since  $V_e$  is strongly concentration dependent, and the concentration of ferrous sites varies with pressure as discussed above, one can understand why  $\Delta V$  varies with pressure. It can be shown that a small value of *B* implies a large negative value of

 $\frac{\partial V_e}{\partial C_{II}}$ 

at low concentration of ferrous sites (low pressure), and strong coupling between adjacent sites, whereas large *B* implies weak coupling between adjacent ions or molecules.

Fig. 3 exhibits conversion data for the basic acetate and acetylacetonate

(4). Both of these ligands are bidentate with each molecule attaching to the iron through two oxygens. The values of *B*, and hence of  $\Delta \overline{V}$ , are significantly larger here than for the halides, and decrease measurably with increasing temperature. On the other hand, ferric oxalate and strontium ferric oxalate (4)  $[Sr_3(Fe(C_2O_4)_3)_2 \cdot 2H_2O]$  also have bidentate ligands attached through oxygen, but both show an increase of  $\Delta \overline{V}$ with temperature (Table 1). It is known that the oxalates reduce photochemically at 1 atmosphere (11, 12) and undergo a series of reactions when

Table 2. Heats of reaction.

Material	Pressure (kbar)	Temper- ature (°K)	$\Delta H(eV)$	
FeCl <sub>3</sub>	sija	323	0.12	
FeCl <sub>3</sub>	sijt.	393	0.18	
FeBra	44	323	0.20	
FeBra	*	393	0.32	
KFeCl <sub>4</sub>	44	323 - 393	0.07	
Fe acetylacetonate	60	325	0.15	
Fe acetylacetonate	60	375	0.25	
Fe acetylacetonate	150	325	0.065	
Fe acetylacetonate	150	375	0.085	
Fe basic acetate	75	398	0.93	
Fe basic acetate	150	398	0.44	
Fe oxalate	25	315	0.19	
Fe oxalate	25	360	0.34	
Fe oxalate	100	315	0.26	
Fe oxalate	100	360	0.42	
Strontium				
Fe oxalate	20	333	0.11	
Strontium				
Fe oxalate	200	333	0.24	
Hemin	20	335	- 0.22	
Hemin	60	335	- 0.11	
Hemin	90	335	- 0.057	
Hematin	40	320	- 0.23	
Hematin	90	320	- 0.052	

\* Independent of pressure